# Installation Instructions for meriLink<sup>™</sup>

### Outline of the steps to install meriLink

- 1. Read these Installation Instructions first.
- 2. Check your computer's compatibility with Microsoft Windows.
- 3. Download and install the meriLink application.

### Check your version of Microsoft Windows

The meriLink program is compatible with these versions of Windows.

- Windows 10
- Windows 8 (8.1)
- Windows 7

### Download and install meriLink setup(.exe)

#### http://content.meriam.com/install/meriLink/setup.exe

**Note:** Different browsers notify you in different ways when a file has downloaded and where to open it.

 Open the setup file and the following dialog box appears. Click Run.

Note: Some of you may see the full file name setup.exe.



2. After you click **Run**, the *meriLink Setup* dialog box appears, click **Install**.



3. Click Install again.

Application Install - Security Warning	×	
Do you want to install this application?	<b>§</b>	
Name: meriLink From (Hover over the string below to see the full domain): content.meriam.com		
Publisher: <u>The Scott Fetzer Company</u>		
<u>I</u> nstall <u>D</u> on	't Install	
While applications from the Internet can be useful, they can potentially harm your computer. If you do not trust the source, do not install this software. <u>More Information</u>		

4. Click OK.



Congratulations. You are ready to use meriLink.

A shortcut for meriLink appears on your desktop.

Click to find the **9R609 meriLink User Manual** or go to the Products Manuals page on www.meriam.com to find the latest manual.

### Error message: meriLink Setup

If this message appears, follow these steps:

- Uninstall the existing version of Microsoft Visual C++ 2015 Redistributable (x86) – 14.0.230.26 on your computer. See the figure below.
- 2. Open the Windows' Control Panel to find and uninstall this version of **Visual C++**.

😵 meriLir	ık Setup	×
<u>^</u>	An error occurred while installing system components for meriLin until all system components have been successfully installed.	ik. Setup cannot continue
Deta	ails <<	Close
Component Visual C++ "14" Runtime Libraries (x86) has failed to install with the following error message: "Another version of this product is already installed. Installation of this version cannot continue. To configure or remove the existing version of this product, use Add/Remove Programs on the Control Panel."		
The follov - Visual C	ving components failed to install: ++ "14" Runtime Libraries (x86)	
See the s for more i	etup log file located at 'C:\Users\rgudgeon\AppData\Local\Tem nformation.	p\VSD3A3E.tmp\install.log'

3. Close the error window and reopen the **setup** file.

# Help

## Meriam Contact Information

#### Address

Meriam 10920 Madison Avenue Cleveland | Ohio | 44102 | USA

#### Telephone

US customers	(800) 817-7849
International customers	+ 1 216 281 1100

#### Fax

US & International customers + 1 216 281 0228

#### E-mail addresses

Return Material Authorization / Service & Repair Department

returnforms@meriam.com

Sales

sales@meriam.com

#### Website

meriam.com

Find a local Meriam representative

Use this map to help you find a Meriam representative.

http://www.meriam.com/representatives-map/